

# *KillTest*

품질은 좋고 서비스도 더욱 좋습니다



# 덤프

<http://www.killtest.kr>

우리는 고객에게 년 동안 무상업데이트 서비스를 제공합니다

**Exam** : **RH302**

**Title** : RHCE (Redhat Certified  
Engineer) On Redhat  
Enterprise Linux 5

**Version** : Demo

### 1.CORRECT TEXT

Change the root Password to redtophat

Answer and Explanation:Boot the system in Single user modeUse the passwd command

### 2.CORRECT TEXT

Dig Server1.example.com, Resolve to successfully through DNS Where DNS server is 172.24.254.254

Answer and Explanation:

```
#vi /etc/resolv.conf
```

```
nameserver 172.24.254.254
```

```
# dig server1.example.com
```

```
#host server1.example.com
```

DNS is the Domain Name System, which maintains a database that can help your computer translate domain names such as www.redhat.com to IP addresses such as 216.148.218.197. As no individual DNS server is large enough to keep a database for the entire Internet, they can refer requests to other DNS servers.

DNS is based on the named daemon, which is built on the BIND (Berkeley Internet Name Domain) package developed through the Internet Software Consortium

Users wants to access by name so DNS will interpret the name into ip address. You need to specify the Address if DNS server in each and every client machine. In Redhat Enterprise Linux, you need to specify the DNS server into /etc/resolv.conf file.

After Specifying the DNS server address, you can verify using host, dig and nslookup commands.

### 3.CORRECT TEXT

Create the partition having 100MB size and mount it on /mnt/neo

Answer and Explanation:

1. Use fdisk /dev/hda " To create new partition.
2. Type n " For New partitions
3. It will ask for Logical or Primary Partitions. Press l for logical.
4. It will ask for the Starting Cylinder: Use the Default by pressing Enter Key.
5. Type the Size: +100M " You can Specify either Last cylinder or Size here.
6. Press P to verify the partitions lists and remember the partitions name.
7. Press w to write on partitions table.
8. Either Reboot or use partprobe command.
9. Use mkfs -t ext3 /dev/hda? Where ? is your partition number
10. Or
11. mke2fs -j /dev/hda? " To create ext3 filesystem.
12. mkdir /mnt/neo
13. vi /etc/fstab
14. Write:
15. /dev/hda? /mnt/neo ext3 defaults 1 2
16. Verify by mounting on current Sessions also:
17. mount /dev/hda? /mnt/neo

### 4 CORRECT TEXT

Your System is going use as a router for 172.24.0.0/16 and 172.25.0.0/16. Enable the IP Forwarding.

Answer and Explanation:

1. echo "1" >/proc/sys/net/ipv4/ip\_forward
2. vi /etc/sysctl.conf  
net.ipv4.ip\_forward=1

/proc is the virtual filesystem, containing the information about the running kernel. To change the parameter of running kernel you should modify on /proc. From Next reboot the system, kernel will take the value from /etc/sysctl.conf.

#### 5.CORRECT TEXT

Some users home directory is shared from your system. Using showmount -e localhost command, the shared directory is not shown. Make access the shared users home directory.

Answer and Explanation:

1. Verify the File whether Shared or not ? : cat /etc/exports
2. Start the nfs service: service nfs start
3. Start the portmap service: service portmap start
4. Make automatically start the nfs service on next reboot: chkconfig nfs on
5. Make automatically start the portmap service on next reboot: chkconfig portmap on
6. Verify either sharing or not: showmount -e localhost
7. Check that default firewall is running on system ? if running flush the iptables using iptables -F and stop the iptables service.

#### 6.CORRECT TEXT

neo user tried by:

```
dd if=/dev/zero of=/home/neo/somefile bs=1024 count=70
```

files created successfully. Again neo tried to create file having 70K using following command:

```
dd if=/dev/zero of=/home/neo/somefile bs=1024 count=70
```

But he is unable to create the file. Make the user can create the file less then 70K.

Answer and Explanation:

Very Tricky question from redhat. Actually question is giving scenario to you to implement quota toneo user. You should apply the quota to neo user on /home that neo user shouldn't occupied space more than 70K.

1. vi /etc/fstab

LABEL=/home /home ext3 defaults,usrquota 0 0 " To enable th quota on filesystem you should mount the filesystem with usrquota for user quota and grpquota for group quota.

2. touch /home/aquota.user "Creating blank quota database file.
3. mount -o remount /home " Remounting the /home with updated mount options. ou can verify that /home is mounted with usrquota options or not using mount command.
4. quotacheck -u /home " Initialization the quota on /home
5. edquota -u neo /home " Quota Policy editor

See the snapshot

Disk quotas for user neo (uid 500):

Filesystem blocks soft hard inodes soft hard

```
/dev/mapper/vo-myvol 2 30 70 1 0 0
```

Can you set the hard limit 70 and soft limit as you think like 30.

Verify using the repquota /home command.

#### 7.CORRECT TEXT

One Logical Volume is created named as myvol under vo volume group and is mounted. The Initial Size of that Logical Volume is 124MB. Make successfully that the size of Logical Volume 245MB without losing any data. The size of logical volume 240MB to 255MB will be acceptable.

Answer and Explanation:

1. First check the size of Logical Volume: `lvdisplay /dev/vo/myvol`
2. Increase the Size of Logical Volume: `lvextend -L+121M /dev/vo/myvol`
3. Make Available the size on online: `resize2fs /dev/vo/myvol`
4. Verify the Size of Logical Volume: `lvdisplay /dev/vo/myvol`
5. Verify that the size comes in online or not: `df -h`

We can extend the size of logical Volume using the `lvextend` command. As well as to decrease the size of Logical Volume, use the `lvresize` command. In LVM v2 we can extend the size of Logical Volume without unmount as well as we can bring the actual size of Logical Volume on online using `ext2online` command.

#### 8.CORRECT TEXT

Quota is implemented on /data but not working properly. Find out the Problem and implement the quota to user1 to have a soft limit 60 inodes (files) and hard limit of 70 inodes (files).

Answer and Explanation:

Quotas are used to limit a user's or a group of users' ability to consume disk space. This prevents a small group of users from monopolizing disk capacity and potentially interfering with other users or the entire system. Disk quotas are commonly used by ISPs, by Web hosting companies, on FTP sites, and on corporate file servers to ensure continued availability of their systems.

Without quotas, one or more users can upload files on an FTP server to the point of filling a filesystem. Once the affected partition is full, other users are effectively denied upload access to the disk. This is also a reason to mount different filesystem directories on different partitions. For example, if you only had partitions for your root (/) directory and swap space, someone uploading to your computer could fill up all of the space in your root directory (/). Without at least a little free space in the root directory (/), your system could become unstable or even crash.

You have two ways to set quotas for users. You can limit users by inodes or by kilobyte-sized disk blocks. Every Linux file requires an inode. Therefore, you can limit users by the number of files or by absolute space. You can set up different quotas for different filesystems. For example, you can set different quotas for users on the /home and /tmp directories if they are mounted on their own partitions.

Limits on disk blocks restrict the amount of disk space available to a user on your system. Older versions of Red Hat Linux included LinuxConf, which included a graphical tool to configure quotas.

As of this writing, Red Hat no longer has a graphical quota configuration tool. Today, you can configure quotas on RHEL only through the command line interface.

1. `vi /etc/fstab`

```
/dev/hda11 /data ext3 defaults,usrquota 1 2
```

2. Either Reboot the System or remount the partition.

Mount -o remount /dev/hda11 /data

3. touch /data/aquota.user

4. quotacheck -ufm /data

5. quotaon -u /data

6. edquota -u user1 /data

and Specified the Soft limit and hard limit on opened file.

To verify either quota is working or not:

Soft limit specify the limit to generate warnings to users and hard limit can't cross by the user. Use the quota command or repquota command to monitor the quota information.

## 9.CORRECT TEXT

One Logical Volume named lv1 is created under vg0. The Initial Size of that Logical Volume is 100MB. Now you required the size 500MB. Make successfully the size of that Logical Volume 500M without losing any data. As well as size should be increased online.

Answer and Explanation:

The LVM system organizes hard disks into Logical Volume (LV) groups. Essentially, physical hard disk partitions (or possibly RAID arrays) are set up in a bunch of equal-sized chunks known as Physical Extents (PE). As there are several other concepts associated with the LVM system, let's start with some basic definitions:

\* Physical Volume (PV) is the standard partition that you add to the LVM mix. Normally, a physical volume is a standard primary or logical partition. It can also be a RAID array.

\* Physical Extent (PE) is a chunk of disk space. Every PV is divided into a number of equal sized PEs. Every PE in a LV group is the same size. Different LV groups can have different sized PEs.

\* Logical Extent (LE) is also a chunk of disk space. Every LE is mapped to a specific PE.

\* Logical Volume (LV) is composed of a group of LEs. You can mount a filesystem such as /home and /var on an LV.

\* Volume Group (VG) is composed of a group of LVs. It is the organizational group for LVM. Most of the commands that you'll use apply to a specific VG.

1. Verify the size of Logical Volume: `lvdisplay /dev/vg0/lv1`

2. Verify the Size on mounted directory: `df -h` or `df -h` mounted directory name

3. Use : `lvextend -L+400M /dev/vg0/lv1`

4. `resize2fs /dev/vg0/lv1` to bring extended size online.

5. Again Verify using `lvdisplay` and `df -h` command.

## 10.CORRECT TEXT

Create one partitions having size 100MB and mount it on /data.

Answer and Explanation:

1. Use `fdisk /dev/hda` To create new partition.

2. Type `n` For New partitions

3. It will ask for Logical or Primary Partitions. Press `l` for logical.

4. It will ask for the Starting Cylinder: Use the Default by pressing Enter Key.

5. Type the Size: `+100M` You can Specify either Last cylinder of Size here.

6. Press `P` to verify the partitions lists and remember the partitions name.

7. Press `w` to write on partitions table.
8. Either Reboot or use `partprobe` command.
9. Use `mkfs -t ext3 /dev/hda?`

Or

`mke2fs -j /dev/hda?` To create ext3 filesystem

10. `vi /etc/fstab`

Write:

`/dev/hda? /data ext3 defaults 1 2`

11. Verify by mounting on current Sessions also:

`mount /dev/hda? /data`

11 CORRECT TEXT

You are new System Administrator and from now you are going to handle the system and your main task is Network monitoring, Backup and Restore. But you don't know the root password. Change the root password to `redhat` and login in default Runlevel.

Answer and Explanation:

When you Boot the System, it starts on default Runlevel specified in `/etc/inittab`:

`id:?:initdefault:`

When System Successfully boot, it will ask for username and password. But you don't know the root's password. To change the root password you need to boot the system into single user mode.

You can pass the kernel arguments from the boot loader.

1. Restart the System.
2. You will get the boot loader GRUB screen.
3. Press `a` and type `1` or `s` for single mode  
`ro root=LABEL=/ rhgb quiet s`
4. System will boot on Single User mode.
5. Use `passwd` command to change.
6. Press `ctrl+d`

12 CORRECT TEXT

There are more than 400 Computers in your Office. You are appointed as a System Administrator. But you don't have Router. So, you are going to use your One Linux Server as a Router. How will you enable IP packets forward?

Answer and Explanation:

1. `/proc` is the virtual filesystem, we use `/proc` to modify the kernel parameters at running time.

`# echo "1" >/proc/sys/net/ipv4/ip_forward`

2. `/etc/sysctl.conf` when System Reboot on next time, `etc/rc.d/rc.sysinit` scripts reads the file `/etc/sysctl.conf`. To enable the IP forwarding on next reboot also you need to set the parameter.

`net.ipv4.ip_forward=1`

Here 0 means disable, 1 means enable.

13.CORRECT TEXT

You Completely Install the Redhat Enterprise Linux 5 on your System. While start the system, it's giving error to load X window System. How will you fix that problem and make boot successfully run X Window System.

Answer and Explanation:

Think while Problems occurred on booting System on Runlevel 5 (X Window)./tmp is full or not Quota is already reached Video card or resolution or monitor is misconfigured.xfs service is running or not.

Do These:

1. `df -h /tmp` " " /tmp is full remove the unnecessary file quota username " " if quota is already reached remove unnecessary file from home directory. Boot the System in runlevel 3. " " you can pass the Kernel Argument from boot loader. Use command: `system-config-display` " " It will display a dialog to configure the monitor, Video card, resolution etc. Set the Default Runlevel 5 in `/etc/inittab` id:5:inittab default:

6. Reboot the System you will get the GUI login Screen.

14 CORRECT TEXT

There are two different networks, 192.168.0.0/24 and 192.168.1.0/24. Your System is in 192.168.0.0/24 Network. One RHEL 5 Installed System is going to use as a Router. All required configuration is already done on Linux Server. Where 192.168.0.254 and 192.168.1.254 IP Address are assigned on that Server. How will make successfully ping to 192.168.1.0/24 Network's Host?

Answer and Explanation:

1. `vi /etc/sysconfig/network`

`GATEWAY=192.168.0.254`

OR

`vi /etc/sysconf/network-scripts/ifcfg-eth0`

`DEVICE=eth0`

`BOOTPROTO=static`

`ONBOOT=yes`

`IPADDR=192.168.0.?`

`NETMASK=255.255.255.0`

`GATEWAY=192.168.0.254`

2. `service network restart`

15 CORRECT TEXT

Make a swap partition having 100MB. Make Automatically Usable at System Boot Time.

Answer and Explanation:

1. Use `fdisk /dev/hda` " " To create new partition.

2. Type `n` " " For New partition

3. It will ask for Logical or Primary Partitions. Press `l` for logical.

4. It will ask for the Starting Cylinder: Use the Default by pressing Enter Key.

5. Type the Size: `+100M` " " You can Specify either Last cylinder or Size here.

6. Press `P` to verify the partitions lists and remember the partitions name. Default System ID is 83 that means Linux Native.

7. Type `t` to change the System ID of partition.

8. Type Partition Number

9. Type 82 that means Linux Swap.

10. Press `w` to write on partitions table.

11. Either Reboot or use `partprobe` command.

12. `mkswap /dev/hda?` To create Swap File system on partition.
13. `swapon /dev/hda?` To enable the Swap space from partition.
14. `free -m` Verify Either Swap is enabled or not.
15. `vi /etc/fstab`  
`/dev/hda? swap swap defaults 0 0`
16. Reboot the System and verify that swap is automatically enabled or not.

#### 16.CORRECT TEXT

You are a System administrator. Using Log files very easy to monitor the system. Now there are 50 servers running as Mail, Web, Proxy, DNS services etc. You want to centralize the logs from all servers into on LOG Server. How will you configure the LOG Server to accept logs from remote host ?

Answer and Explanation:

By Default system accept the logs only generated from local host. To accept the Log from other host configure:

1. `vi /etc/sysconfig/syslog`

```
SYSLOGD_OPTIONS="-m 0 -r"
```

Where

- m 0 disables 'MARK' messages.
- r enables logging from remote machines
- x disables DNS lookups on messages received with -r

2. `service syslog restart`

#### 17 CORRECT TEXT

You are giving the debug RHCT exam. The examiner told you that the password of root is redhat. When you tried to login displays the error message and redisplayed the login screen. You changed the root password, again unable to login as a root. How will you make Successfully Login as a root.

Answer and Explanation:

When root unable to login into the system think:

1. Is password correct?
2. Is account expired?
3. Is terminal Blocked?

Do these Steps: Boot the System on Single user mode. Change the password. Check the account expire date by using `chage -l root` command.

If account is expired, set net expire date: `chage -E "NEVER" root`

1. Check the file `/etc/securetty` Which file blocked to root login from certain terminal
2. If terminal is deleted or commented write new or uncomment.
3. Reboot the system and login as a root.

#### 18.CORRECT TEXT

You are giving RHCT Exam and in your Exam paper there is a question written, make successfully ping to 192.168.0.254.

Answer and Explanation:

In Network problem thinks to check:

1. IP Configuration: use `ifconfig` command either IP is assigned to interface or not?

2. Default Gateway is set or not?
3. Hostname is set or not?
4. Routing problem is there?
5. Device Driver Module is loaded or not?
6. Device is activated or not?

Check In this way:

1. use ifconfig command and identify which IP is assigned or not.
2. cat /etc/sysconfig/network " What, What is written here. Actually here are these parameters  
NETWORKING=yes or no  
GATEWAY=x.x.x.x  
HOSTNAME=?  
NISDOMAIN=?  
-Correct the file
3. Use vi /etc/sysconfig/network-scirpts/ifcfg-eth0 and check the proper options  
DEVICE=eth0  
ONBOOT=yes  
BOOTPROTO=static  
IPADDR=x.x.x.x  
NETMAKS=x.x.x.x  
GATEWAY=x.x.x.x
4. Use service network restart or start command

#### 19 CORRECT TEXT

Set the Hostname station?.example.com where ? is your Host IP Address.

Answer and Explanation:

1. hostname station?.example.com " This will set the host name only for current session. To set hostname permanently.
2. vi /etc/sysconfig/network  
HOSTNAME=station?.example.com
3. service network restart

#### 20 CORRECT TEXT

The System you are using is for NFS (Network File Services). Some important data are shared from your system. Make automatically start the nfs and portmap services at boot time.

Answer and Explanation:

We can control the services for current session and for next boot time also. For current Session,we use service servicename start or restart or stop or status. For automatically on next reboot time:

1. chkconfig servicename on or off

eg: chkconfig nfs on

chkconfig portmap on

or

ntsysv

Select the nfs and portmap services.

2. Reboot the system and identify whether services are running or not.

### 21.CORRECT TEXT

There is one partition /dev/hda14 mounted on /data. The owner of /data is root user and root group. And Permission is full to owner user, read and execute to group member and no permission to others. Now you should give the full permission to user user1 without changing pervious permission.

Answer and Explanation:

We know that every files/directories are owned by certain user and group. And Permissions are defines to owner user, owner group and other.

-rwxr-x--- Full permission to owner user, read and write to owner group and no permission to others.

According to question: We should give the full permission to user user1 without changing the previous permission.

ACL (Access Control List), in ext3 file system we can give permission to certain user and certain group without changing previous permission. But that partition should mount using acl option.

Follow the stepsvi /etc/fstab

/dev/hda14 /data ext3 defaults,acl 0 1Either Reboot or use: mount -o remount /datasetfacl -m u:user1:rwx /dataVerify using: getfacl /data

### 22.CORRECT TEXT

There are two different networks 192.168.0.0/24 and 192.168.1.0/24. Where 192.168.0.254 and 192.168.1.254 IP Address are assigned on Server. Verify your network settings by pinging 192.168.1.0/24 Network's Host.

Answer and Explanation:

1. vi /etc/sysconfinf/network

NETWORKING=yes

HOSTNAME=station?.example.com

GATEWAY=192.168.0.254

2. service network restart

Or

1. vi /etc/sysconfig/network-scripts/ifcfg-eth0

DEVICE=eth0

ONBOOT=yes

BOOTPROTO=static

IPADDR=X.X.X.X

NETMASK=X.X.X.X

GATEWAY=192.168.0.254

2. ifdown eth0

3. ifup eth0

### 23.CORRECT TEXT

Your system is giving error while booting on Runlevel 5 . Make successfully boot your system in runlevel 5.

Answer and Explanation:

While you load the X Window System, you will get the problem. To troubleshoot follow the following steps:

1. Check the /tmp is full ?
2. Check your quota, hard limit is already crossed ?
3. Check xfs service is running ?
4. Boot the system on runlevel 3 and execute the system-config-display command
5. Edit the /etc/inittab to set default runlevel 5.

id:5:initdefault:

#### 24.CORRECT TEXT

Your System is configured in 192.168.0.0/24 Network and your nameserver is 192.168.0.254. Make successfully resolve to server1.example.com.

Answer and Explanation:

Very Easy question, nameserver is specified in question,

1. vi /etc/resolv.conf  
nameserver 192.168.0.254
2. host server1.example.com

#### 25 CORRECT TEXT

One Package named zsh is dump on ftp://server1.example.com under /pub/updates directory and your FTP server is 192.168.0.254. Install the package zsh.

Answer and Explanation:

1. rpm -ivh ftp://server1/example.com/pub/updates/zsh-\*
- or
1. Login to ftp server : ftp ftp://server1.example.com using anonymous user.
  2. Change the directory: cd pub and cd updates
  3. Download the package: mget zsh-\*
  4. Quit from the ftp prompt : bye
  5. Install the package
  6. rpm -ivh zsh-\*
  7. Verify either package is installed or not : rpm -q zsh

#### 26 CORRECT TEXT

Add a new logical partition having size 100MB and create the /data which will be the mount point for the new partition.

Answer and Explanation:Use fdisk /dev/hda "n" To create new partition.Type n "n" For New partitionsIt will ask for Logical or Primary Partitions. Press l for logical.It will ask for the Starting Cylinder: Use the Default by pressing Enter Key.Type the Size: +100M "n" You can Specify either Last cylinder of Size here.Press P to verify the partitions lists and remember the partitions name.Press w to write on partitions table.Either Reboot or use partprobe command.Use mkfs -t ext3 /dev/hda?Ormk2fs -j /dev/hda? "n" To create ext3 filesystem.vi /etc/fstabWrite:/dev/hda? /data ext3 defaults 0 0Verify by mounting on current Sessions also:mount /dev/hda? /data

#### 27.CORRECT TEXT

There is a server having 172.24.254.254 and 172.25.254.254. Your System lies on 172.24.0.0/16. Make successfully ping to 172.25.254.254 by Assigning following IP: 172.24.0.x Where x is your station number.

Answer and Explanation:

1. vi /etc/sysconfig/network-scripts/ifcfg-eth0

DEVICE=eth0

BOOTPROTO=static

ONBOOT=yes

IPADDR=x.x.x.x

NETMASK=x.x.x.x

2. Enter the IP Address as given station number by your examiner: example: 172.24.0.1

3. Enter Subnet Mask

4. Enter Default Gateway and primary name server

5. press on ok

6. ifdown eth0

7. ifup eth0

8. verify using ifconfig

In the lab server is playing the role of router, IP forwarding is enabled. Just set the Correct IP and gateway, you can ping to 172.25.254.254.

28.CORRECT TEXT

Successfully resolv to server1.example.com where your DNS server is 172.24.254.254

Answer and Explanation:

1. vi /etc/resolv.conf

nameserver 172.24.254.254

2. host server1.example.com

29 CORRECT TEXT

Make Successfully Resolve to server1.example.com where DNS Server is 192.168.0.254.

Answer and Explanation: 1. vi /etc/resolv.conf

Write : nameserver 192.168.0.254

30.CORRECT TEXT

One Logical Volume is created named as myvol under vo volume group and is mounted. The Initial Size of that Logical Volume is 400MB. Make successfully that the size of Logical Volume 200MB without losing any data. The size of logical volume 200MB to 210MB will be acceptable.

Answer and Explanation:

1. First check the size of Logical Volume: `lvdisplay /dev/vo/myvol`

2. Make sure that the filesystem is in a consistent state before reducing:

`# fsck -f /dev/vo/myvol`

3. Now reduce the filesystem by 200MB.

`# resize2fs /dev/vo/myvol 200M`

4. It is now possible to reduce the logical volume.

`#lvreduce /dev/vo/myvol -L 200M`

4. Verify the Size of Logical Volume: `lvdisplay /dev/vo/myvol`

5. Verify that the size comes in online or not: `df -h`